GAUSS[™] Data Tool 10

Information in this document is subject to change without notice and does not represent a commitment on the part of Aptech Systems, Inc. The software described in this document is furnished under a license agreement or nondisclosure agreement. The software may be used or copied only in accordance with the terms of the agreement. The purchaser may make one copy of the software for backup purposes. No part of this manual may be reproduced or transmitted in any form or by any means, electronic or mechanical, including photocopying and recording, for any purpose other than the purchaser's personal use without the written permission of Aptech Systems, Inc.

©Copyright Aptech Systems, Inc. Black Diamond, WA 1997-2010 All Rights Reserved.

GAUSS, **GAUSS Engine** and **GAUSS Light** are trademarks of Aptech Systems, Inc. Other trademarks are the property of their respective owners.

Part Number: 006913 Version 10 Documentation Revision: 949

May 28, 2010



Vertrieb durch: **ADDITVE Soft- und Hardware für Technik und Wissenschaft GmbH** Max-Planck-Straße 22b • 61381 Friedrichsdorf http://www.additive-net.de/gauss • eShop: http://eshop.additive-net.de Verkauf: +49-6172-5905-30 • gauss@additive-net.de

Contents

1 Getting Started

1.1	Overview	W	1-1					
1.2	GAUSS Data Tool Basics							
1.3	User Interfaces							
	1.3.1	Windows Graphical User Interface	1-4					
	1.3.2	Terminal Interface	1-7					
1.4	Scalar a	nd Element by Element Operations	1-11					
1.5	Simulating Data							

2 Import

Overview	Ν	2-1
ASCII Fi	le Conversion	2-1
2.2.1	Command Summary	2-2
2.2.2	Commands	2-4
2.2.3	Examples	2-21
Excel Fil	le Conversion	2-24
2.3.1	Command Summary	2-24
2.3.2	Example	2-25
2.3.3	Commands	2-27
	ASCII Fi 2.2.1 2.2.2 2.2.3 Excel Fi 2.3.1 2.3.2	2.2.3 Examples Excel File Conversion 2.3.1 Command Summary 2.3.2 Example

3 Export

3.1	Overviev	V	3-1
3.2	ASCII Fi	le Conversion	3-1
	3.2.1	Command Summary	3-2
	3.2.2	Commands	3-2
	3.2.3	Examples	3-7

GAUSS Data Tool

3.3	Excel Fi	le Conversion	3-9
	3.3.1	Command Summary	3-10
	3.3.2	Example	3-11
	3.3.3	Commands	3-12

4 Statement Reference

add	
allops	
cat	
cd	4-5
cleanup	
close	
code	
commit	4-10
сору	
create	4-11
delete	
dotops	
drop	4-14
export	
frename	
g	
import	
impute	
keep	4-20
ld	4-20
lv	4-21
merge	4-22
model	4-23

Contents

nouse .										•			•										4-	25
open									•	•			•									•	4-	26
р				•				•															4-	27
pwd				•				•															4-	28
q, quit .				•				•						•	 •							•	4-	29
recode .				•				•															4-	29
recover				•				•						•	 •							•	4-	32
remove				•				•						•	 •							•	4-	32
report .				•			•	•		•				•								•	4-	33
rollback				•			•	•		•				•								•	4-	35
sample				•				•															4-	36
select .				•			•	•		•				•								•	4-	37
show				•				•															4-	38
sort				•			•	•		•				•								•	4-	38
split									•	•			•										4-	39
stack				•			•	•		•				•								•	4-	40
stats				•			•	•		•				•								•	4-	41
use									•	•			•										4-	42
vrename				•				•															4-	43
vtype			•	•		•	•	•	•	•				•							•	•	4-	44

Index

Getting Started

1.1 Overview

GAUSS Data Tool (GDT) is a standalone program for working with GAUSS data sets. GDT loads columns of a data set into a workspace as vectors where they can be transformed or modified using simple intuitive statements. A variety of simulation models can create new data sets and, using single or multiple imputations, missing data can be included in new versions of data sets.

1.2 GAUSS Data Tool Basics

Within the **GDT** session, **GDT** creates a workspace for each open data set and then loads that workspace by placing each data set variable in a separate $N \times 1$ column vector.

For a list of available GDT commands, enter:

help

For help on a specific command, enter:

help command_name

In the Windows GUI, to display the dialog interface for a command, type:

command_name -

For example:

sort -

To list the data sets in the current directory, enter:

1d

To change directories, enter:

cd *directory*

To open a data set, enter:

open *file_name*

Getting Started

where *file_name* is the name of the file containing the desired data set in the

Or

open *file_path* where *file_path* is the path of the desired data set.

Example:

current directory.

open freqdata open /data/freqdata

Each open data set has a *handle*, which is used to refer to the data set in many **GDT** commands. Most GDT commands work on the active data set. A data set becomes the active data set when it is opened or specified in the **use** command.

To make an open data set the active data set, enter:

use handle

where *handle* is the handle of an open data set.

To see the list of open data sets, enter:

open

In the resulting list, the *handle* is shown at the left while the active data set is indicated with a right angle bracket (>). An asterisk (*) indicates the data has been modified since the data set was opened or committed.

For a list of variables in the active data set, enter:

lv

For descriptive statistics on the active data set, enter:

stats

Transformations on the variables are possible with simple assignment statements.

Example: The following statement modifies the active data set variable x1 by changing each element to its exponential.

x1 = exp(x1)

To save active data set changes to the disk data set file, enter:

commit

To discard active data set changes without saving them to the disk data set file, enter:

rollback

1.3 User Interfaces

1.3.1 Windows Graphical User Interface

Screen Layout

Within the Windows **GDT** session, program output is displayed in the screen area above the **GDT** prompt. This area is read-only and keyboard entries here will automatically

move the cursor to the **GDT** prompt and begin input. However, text in the output area can be copied and pasted to the input area (the **GDT** prompt line and any lines below it) or to other Windows applications.

Basic Input Process

GDT commands and statements are entered at the **GDT** prompt. Pressing [ENTER] after entering a command or statement causes that statement or command to be executed.

Each executed command and statement of the **GDT** session is recorded in the command history. To retrieve a previously issued command or statement, use [CTRL]+[UP ARROW] and [CTRL]+[DOWN ARROW] to scroll backward and forward through the command history. The command history only contains commands and statements from the current **GDT** session.

The following are graphical interface commands:

cls	Clears the entire screen.					
cd	Changes the current directory; if no arguments are included, the current directory is set to the user's home directory.					
dir	Display directory listing-similar to the DOS 'dir' command.					
dos, shell	s, shell Spawns a DOS shell.					
explore	Invoke the Windows Explorer file browser application.					
[CTRL]+[UP ARROW] Scrolls backward through the command history to reuse a previously issued command.						
[CTRL]+[DOWN ARROW] Scrolls forward through the command history to reuse a previously issued command.						

Long lines can be extended by adding a \setminus to the end of a line.

Multi-line Input

The syntax for several GDT statements requires multiple line entries.

To enter multi-line mode, do one of the following steps at the GDT prompt.

Press [CTRL]+[ENTER].

Or

Enter a backslash (\).

Result: **GDT** enters multi-line mode by creating an input line with a right angle bracket (>) at the left.

After each line entry, press [ENTER].

Result: GDT adds a new input line.

To edit a line entry, move the cursor to the desired line then modify the line content.

When all line entries have been entered and desired changes made, exit multi-line mode by doing one of the following steps:

Press [ESC].

Result: **GDT** exits multi-line mode without saving the line entries to the command history or executing them.

Or

Press [ENTER] on the new empty line.

Result: **GDT** saves line entries to the command history then exits multi-line mode without executing the lines.

Or

Enter a forward slash (/) on the new empty line.

Result: **GDT** saves the line entries to the command history, exits multi-line mode, and executes the lines.

Note: The forward slash (/) does not become a line entry.

1.3.2 Terminal Interface

Screen Layout

Within the Terminal **GDT** session, program output is displayed in the screen area above the **GDT** prompt. Since this is a read-only area, the cursor can only be placed within the **GDT** prompt input area. However, text in the output area can be copied and pasted to the **GDT** prompt input area or other Terminal applications.

Basic Input Process

GDT commands and statements are entered at the **GDT** prompt. Pressing [ENTER] after entering a command or statement causes that statement or command to be executed.

Long lines can be extended by adding a \setminus to the end of a line.

Multi-line Input

The syntax for several GDT statements requires multiple line entries.

Several line-editing commands reference the current line. The current line is the last line in the buffer that was accessed.

To enter multi-line mode:

Enter a backslash $(\)$ all by itself at the **GDT** prompt.

Result: **GDT** enters multi-line mode by creating an input line with a line number at the left; this line number is used when referencing a particular line in other line-editing commands.

After each line entry, press [ENTER].

Result: **GDT** adds the line entry to the buffer and creates a new input line with an incremented line number.

When all line entries have been entered, exit multi-line mode by doing one of the following steps.

Press [ENTER] at the new input line.

Result: **GDT** exits multi-line mode without executing the buffer content.

Or

Enter a forward slash (/) on the new empty line.

Getting Started

Result: **GDT** exits multi-line mode and executes the buffer content. Note: The forward slash does not become a line entry.

Buffer content remains available for execution or editing until multi-line mode is entered again or the **clear** line-editing command is entered.

Edit the buffer content by entering the following commands in regular (non-multi-line) mode.

a	Appends text to the end of the current line.
del [<i>n</i>]	Deletes the current line or line number <i>n</i> .
clear	Deletes all lines from the line buffer.
ia	Inserts a line after the current line and makes the new line the current line.
ib	Inserts a line before the current line and makes the new line the current line.
1	Lists all line entries in the buffer; the asterisk (*) in the list indicates which line is the current line.
line no.	Lists the specified line number and makes it the current line.
/	Executes previous buffer contents.
\	Clears previous buffer contents and enters multi-line mode.

The following non-line-editing commands are entered in multi-line mode.

/	Exits multi-line mode and executes the buffer contents; does not become a line entry.
[ENTER]	Exits multi-line mode without executing the buffer content; buffer content remains available for execution.

Example

Windows Graphical User Interface (GUI):

```
( gdt . ) \
> model linear
> file test
> depvar Y1
> indvar X1,X2
> beta .5,.5
> open
> /
( gdt test . )
```

Terminal Interface

Simple multiple line entry:

(gdt) \
1 model linear
2 file test
3 depvar Y1
4 indvar X1,X2
5 beta .5,.5
6 open
7 /

Line entry and editing:

(gdt test .)

```
(gdt.) \
1
  This is line one.
2
  This is line two.
3
  This is line three
4
(gdt.) 1
1
  This is line one.
2
  This is line two.
3* This is line three
(gdt .) a this is appended to line three
3* This is line threethis is appended to line three
(gdt.) 1
1 This is line one.
  This is line two.
2
3* This is line threethis is appended to line three
( gdt . ) 1
1* This is line one.
(gdt.) 1
1* This is line one.
2 This is line two.
3 This is line threethis is appended to line three
(gdt .) del 3
(gdt.) 1
1* This is line one.
2 This is line two.
(gdt .) ib This is the new line one
(gdt.) 1
1* This is the new line one
2
  This is line one.
3 This is line two.
(gdt . )
```

1.4 Scalar and Element by Element Operations

GAUSS has two versions of certain operators:

Scalar-returning operators, like >=, return a single 1 or 0 (true or false) result depending on whether every element in the left operand matches the comparison requirements with the corresponding elements in the right operand.

Example: $\mathbf{z} = \mathbf{x} \ge \mathbf{y}$

Result:

z will be set to 1 if every element in *x* is >= the corresponding element in *y*.

z will be set to 0 if any element in x is not >= the corresponding element in y.

Element by element operators, like .>=, return a matrix whose values are 1 or 0 (true or false) depending on whether the elements in the left operand match the comparison requirements with the corresponding elements in the right operand.

Example: $\mathbf{z} = \mathbf{x}$. >= \mathbf{y}

Result: Matrix *z* is created as follows:

For every element in x that is >= the corresponding y element, the corresponding z element is set to 1.

For every element in x that is not >= the corresponding y element, the corresponding z element is set to 0.

The **allops** and **dotops** commands toggle between non-dot (scalar) and dot (element by element) interpretations of these operators in transformation expressions. This affects comparison and logical operators as well as * and /.

Example:

With **allops** in effect, $\mathbf{x1} \ge \mathbf{x2}$ will return a scalar result and $\mathbf{x1} \ge \mathbf{x2}$ will return an element by element result.

With **dotops** in effect, $\mathbf{x1} \ge \mathbf{x2}$ will behave the same as $\mathbf{x1} \ge \mathbf{x2}$, which returns an element by element result.

Code inside procedures is not affected by this setting.

For a more detailed discussion of element by element operations, refer to the *Element by Element Operators* section of the **GAUSS Users Guide**.

1.5 Simulating Data

The **model** command is used to generate simulated data sets. The syntax for a default simulation is:

model model_name

where *model_name* is the name of an available model.

For a complete list of available model names for your GDT version, enter:

help model

For help about a specific model, enter:

help model model_name

Each model type has a variety of options that are available for generating simulated data with specific properties. These options are specified using multi-line mode, described in *User Interfaces* (Section1.3).

Example:

(gdt) \
1 model arima
2 file arsim
3 depvar returns
4 indvar x1,x2
5 vcx 1, .4, 1
6 ar .3, .1
7 ma .1
8 open
9 /

ARIMA

The underlying model is as follows:

$$\Phi(L)(1-L)^d y_t = X\beta + \Theta(L)\epsilon_t$$

where L is the lag operator, and

$$\Phi(L) = 1 - \phi_1 L - \phi_2 L^2 - \dots - \phi_p L^p$$

$$\Theta(L) = 1 + \theta_1 L + \theta_2 L^2 + \dots + \theta_q L^q$$

and d is the level of integration.

Getting Started

GARCH

The underlying model is as follows:

$$\epsilon_t = y_t - x_t \beta - \delta \sigma_t$$

where δ is an "in mean" coefficient

Define

$$\epsilon_t \equiv \eta_t \sigma_t$$

where $E(\eta_t) = 0$, $Var(\eta_t) = 1$, and

$$\sigma_t^2 = \omega + \alpha_1 \sigma_{t-1}^2 \dots \alpha_p \sigma_{t-p}^2 + \epsilon_t + (\beta_1 + \tau_1 \zeta(\epsilon_{t-1})) \epsilon_{t-1} \dots + (\beta_q + \tau_q \zeta(\epsilon_{t-q})) \epsilon_{t-q}$$

where τ_t are "asymmetry" coefficients and

$$\zeta(\epsilon_t) = \begin{cases} 1 & : \quad \epsilon_t < 0 \\ 0 & : \quad \epsilon_t >= 0 \end{cases}$$

LINEAR

The underlying model is as follows:

$$y = x\beta + \epsilon$$

where y is $N \times L$, x is $N \times K$, β is $K \times L$, ϵ is $N \times L$

LOGIT

Binary outcomes are generated in accordance with:

$$Pr(y = k|x) = \frac{e^{k\mu}}{1 + e^{\mu}}$$

where k = 0, 1, and $\mu = x\beta$

If a random error term is selected then $\mu = x\beta + \epsilon$

ORDLOGIT

Ordered outcomes are generated in accordance with:

$$Pr(y = m|x) = \Lambda(\tau_m - \mu) - \Lambda(\tau_{m-1} - \mu)$$

where $\mu = x\beta$, and

$$\Lambda(z) = \frac{e^z}{1 + e^z}$$

If a random error term is selected then $\mu = x\beta + \epsilon$

ORDPROBIT

Ordered outcomes are generated in accordance with:

$$Pr(y = m|x) = \Phi(\tau_m - \mu) - \Phi(\tau_{m-1} - \mu)$$

where $\mu = x\beta$, and

$$\Phi(z) = \frac{1}{\sqrt{2\pi}} \int_{\infty}^{z} e^{-\frac{t^2}{2}} dt$$

If a random error term is selected then $\mu = x\beta + \epsilon$

PROBIT

Binary outcomes are generated in accordance with:

$$Pr(y=1|x) = \frac{1}{\sqrt{2\pi}} \int_{\infty}^{\mu} e^{-\frac{t^2}{2}} dt$$

where Pr(y = 0|x) = 1 - Pr(y = 1|x), and $\mu = x\beta$.

If a random error term is selected then $\mu = x\beta + \epsilon$

Import 2

2.1 Overview

import is a multi-line **GDT** command that converts data files into **GAUSS** data sets. It currently supports conversion from both ASCII and Excel files.

2.2 ASCII File Conversion

Import may be used to convert both delimited and packed ASCII files. To execute, enter

import ascii

as the first line of a multi-line statement. Each succeeding line should contain a subcommand.

2.2.1 Command Summary

The following subcommands are supported for importing ASCII files:

append	Append data to an existing file.
cmdfile	The name of an import command file to run.
complex	Treat data as complex variables.
dateformat	Specify date format. Can be overridden on per variable basis.
delimit	Specify delimiter in ASCII input file.
input	The name of the ASCII input file.
invar	Input file variables (column names).
invarline	Get input file variables from specified line in input file.
msym	Specify missing value character.
nocheck	Do not check data type or record length.
open	Open data set after conversion.
output	The name of the GAUSS data set to be created.
outtyp	Output data type.
outvar	List of variables to be included in output file.
skip	Skip specified number of lines from beginning of input file.
typecase	Change case of variable names in output file to reflect data type.
vartype	Data types of input file variables.

vartypeline Get data types of input file variables from specified line in input file.

The principle commands for converting an ASCII file that is delimited with spaces, commas, or tabs are given in the following example:

(gdt) \
1 import ASCII
2 input agex.asc
3 output agex
4 invar \$ Race # Age Pay %('MO/DD/YYYY') Hiredate \$ Sex Region
5 outvar Region Age Sex Pay
6 outtyp d
7 /

From this example, a soft delimited ASCII file agex.asc is converted to a double precision GAUSS data set agex.dat. The input file has six variables, and thus it will be interpreted as having six columns:

column	name	data type
1	Race	character
2	Age	numeric
3	Pay	numeric
4	Hiredate	date
5	Sex	character
6	Region	character

The output file will have 4 columns since the first and the fourth columns of the input file (Race and Hiredate) are not included in the output variables. The columns of the output file are:

column	name	data type
1	Region	character
2	Age	numeric
3	Sex	character
4	Pay	numeric

The variable names are saved in the file header. By default, their case will be preserved.

The \$ in the **invar** statement specifies that the variables that follow are character type. The # specifies numeric, and the % specifies date. If a % is not followed by a date format string, then the default will be used. The default date format string is 'YYYY-MO-DD'. See vartype for more information on valid formats for date variables. If no variable type is specified in an **invar** statement, the default is numeric.

Comments in **import** command files begin with // and continue to the end of the line.

2.2.2 Commands

A detailed explanation of each subcommand follows.

append

Instructs **import** to append the converted ASCII data to an existing data set:

append

No assumptions are made regarding the format of the existing file. You should make certain that the number, order and type of data converted match the existing file. **import** creates v96 format data files, so it will only append to v96 format data files.

• cmdfile

Specifies the name of an **import** command file, which contains the subcommands for **import**. The full path name can be used in the file specification.

For example, the command:

cmdfile data.cmd

will expect an ASCII command file in the current working directory or the **GDT** source path.

For Windows the command:

output \research\data\myfile.cmd

creates the file myfile.cmd on the \research\data directory, or on UNIX,

cmdfile /research/data/myfile.cmd

specifies a file to be located in the /research/data directory.

You may use **cmdfile** in a **GDT** session as follows:

(gdt) \
1 import ASCII
2 cmdfile myfile.cmd
3 /

In this example, **import** will find and run the myfile.cmd file in the current working directory. The command file should contain all of the **import** subcommands needed for the translation, with a semicolon on the end of each subcommand. **import** command files

support a superset of the commands available in an **ATOG** command file, and **GDT** will execute **ATOG** command files unchanged with the exception that the default type for the output data set is double precision.

For example, myfile.cmd could read as follows:

input day1.asc; output day1; invarline 1; vartype # # \$ # \$; skip 1;

• complex

Instructs **import** to convert the ASCII file into a complex **GAUSS** data set:

complex

Complex **GAUSS** data sets are stored by rows, with the real and imaginary parts interleaved, element by element. **import** assumes the same structure for the ASCII input file, and will thus read TWO numbers out for EACH variable specified.

complex cannot be used with packed ASCII files.

dateformat

Specifies the format string to be used for inputting date data within the current **import** job. **dateformat** may be overridden on a per variable basis by including a date format string after the % type specifier for that variable. If no date format string is specified with either **dateformat** or **vartype**, then the default will be used. The default date format string is 'YYYY-MO-DD'.

This example:

dateformat 'MO/DD/YYYY'
invar \$ Name # Age % Bdate %('HH:MI:SS') Btime

indicates that the format string 'MO/DD/YYYY' should be used to input the *Bdate* variable, while 'HH:MI:SS' should be used to input *Btime*.

A date format string must contain a single delimiter between each element and be enclosed by single quotes. The following date elements are supported:

YYYY	4 digit year
YR	Last two digits of year
MO	Number of month, 1-12
DD	Day of month, 1-31
HH	Hour of day, 0-23
MI	Minute of hour, 00-59
SS	Second of minute, 00-59

If *YR* is specified and the two-digit year is less than or equal to 37, then 2000 will be added to it. Otherwise, 1900 will be added.

• delimit

Specifies the delimiter in the ASCII input file. The format is as follows:

```
delimit (d, N)
      or
delimit (d)
```

where *d* is the delimiter. The second parameter is the letter N. If present, it indicates that **import** should expect to find the same number of delimiters as elements (variables * observations) in the ASCII file. If the parameter is not present, **import** will expect no delimiter after the last element in the file. See the *Hard Delimited ASCII File* section under the **invar** command for more information.

• input

Specifies the file name of the ASCII file to be converted. The full path name can be used in the file specification.

For example, the command:

input data.raw

will expect an ASCII data file in the current working directory.

In Windows the command:

input \research\data\myfile.asc

specifies a file to be located in the \research\data subdirectory, whereas on UNIX

input /research/data/myfile.asc

specifies a file to be located in the /research/data directory.

• invar

Soft Delimited ASCII Files

Soft delimited files may have spaces, commas, tabs, or linefeeds as delimiters between elements. Two or more consecutive delimiters with no data between them are treated as one delimiter.

invar Age \$ Name Sex # Pay %('MO/DD/YYYY') Hdate Var[1:10] X[005]

column	name	data type
1	Age	numeric
2	Name	character
3	Sex	character
4	Pay	numeric
5	Hdate	date
6	Var01	numeric
7	Var02	numeric
8	Var03	numeric
9	Var04	numeric
10	Var05	numeric
11	Var06	numeric
12	Var07	numeric
13	Var08	numeric
14	Var09	numeric
15	Var10	numeric
16	X001	numeric
17	X002	numeric
18	X003	numeric
19	X004	numeric
20	X005	numeric

The **invar** command above specifies the following variables:

As the input file is translated, the first 20 elements will be interpreted as the first row (observation), the next 20 will be interpreted as the second row, and so on. If the number of elements in the file is not evenly divisible by 20, the final incomplete row will be dropped and a warning message will be given.

Hard Delimited ASCII Files

Hard delimited files have a printable character as a delimiter between elements. Two delimiters without intervening data between them will be interpreted as a missing. If n is

specified as a delimiter, the file should have one element per line and blank lines will be considered missings. Otherwise, delimiters must be printable characters. The dot '.' is illegal and will always be interpreted as a missing value. To specify the backslash as a delimiter, use $\$. If $\$ r is specified as a delimiter, the file will be assumed to contain one case or record per line with commas between elements and no comma at the end of the line.

For hard delimited files the **delimit** subcommand is used with the **invar** command. The **delimit** subcommand has two optional parameters. The first parameter is the delimiter; the default is a comma. The second parameter is the letter **N**. If present, it indicates that **import** should expect to find the same number of delimiters as elements (variables * observations) in the ASCII file. If the parameter is not present, **import** will expect no delimiter after the last element in the file.

This example:

invar delimit(, N) \$ name # var[5]

will expect a file like this:

BILL ,	222.3,	123.2,	456.4,	345.2,	533.2,
STEVE,	624.3,	340.3,	,	624.3,	639.5,
TOM ,	244.2,	834.3,	602.3,	333.4,	822.5,

This example:

invar delimit(,) \$ name # var[5]

or

invar delimit \$ name # var[5]

will expect a file like this:

BILL222.3,123.2,456.4,345.2,533.2,STEVE,624.3,340.3,,624.3,639.5,TOM,244.2,834.3,602.3,333.4,822.5

The difference between specifying N or N-1 delimiters can be seen here:

456.4, 345.2, 533.2, , 624.3, 639.5, 602.3, 333.4,

If the **invar** statement had specified 3 variables and **N-1** delimiters, this file would be interpreted as having three rows containing a missing in the 2,1 element and the 3,3 element like this:

456.4 345.2 533.2 . 624.3 639.5 602.3 333.4 .

If **N** delimiters had been specified, this file would be interpreted as having two rows, and a final incomplete row that is dropped:

456.4 345.2 533.2 . 624.3 639.5

The spaces were shown only for clarity and are not significant in delimited files so:

BILL, 222.3, 123.2, 456.4, 345.2, 533.2, STEVE, 624.3, 340.3, 624.3, 639.5, TOM, 244.2, 834.3, 602.3, 333.4, 822.5 would work just as well. Linefeeds are significant only if n is specified as the delimiter, or when using r.

This example:

```
invar delimit(\r) $ name # var[5]
```

will expect a file with no comma after the final element in each row:

BILL ,	222.3,	123.2,	456.4,	345.2,	533.2
STEVE,	624.3,	340.3,	245.3,	624.3,	639.5
TOM ,	244.2,	834.3,	602.3,	333.4,	822.5

Packed ASCII Files

Packed ASCII files must have fixed length records. The **record** subcommand is used to specify the record length and variables are specified by giving their type, starting position, length, and the position of an implicit decimal point if necessary.

Note that **outvar** is not used with packed ASCII files. Instead, **invar** is used to specify only those variables to be included in the output file.

For packed ASCII files the syntax of the **invar** command is as follows:

invar record=reclen (format) variables (format) variables

where,

reclen	the total record length in bytes, including the final carriage return/linefeed if applicable. Records must be fixed length.
format	(<i>start,length.prec</i>) where:

start po	starting position of the field in the record, 1 is the first sition. The default is 1.
length	length of the field in bytes.
prec	optional; a decimal point will be inserted automatically

prec places in from the RIGHT edge of the field.

If several variables are listed after a format definition, each succeeding field will be assumed to start immediately after the preceding field. If an asterisk is used to specify the starting position, the byte following the last field will be assumed. An asterisk in the length position will leave both length and prec unchanged from the previous settings. This is illegal: (3,8.*).

The type change characters \$, # and % are used to specify character, numeric, and date types respectively. If % is indicated, it should be followed by a date format string and then the variable format. See **dateformat** for valid date formats. Since fields in packed ASCII files must have a fixed length, date data must contain two digit months, days and hours or be padded with spaces to the correct field length.

Any data in the record that is not defined in a format is ignored.

The examples below assume a 42-byte record with a carriage return/linefeed occupying the last 2 bytes of each record. The data below can be interpreted in different ways using different **invar** statements:

	ABCDEFGHIJ01-23-200312345678901234567890 <cr><lf></lf></cr>					
		1	I	I		
position	1	10	20	30	40 41 42	

This example:

invar record=42 \$(1,3) group %('MO-DD-YYYY',11,10) deadline #(*,4.2) x[3]

will result in:

variable	value	type
group	ABC	character
deadline	01-23-2003	date
x1	12.34	numeric
x2	56.78	numeric
x3	90.12	numeric

In the **GAUSS** data set, date columns are stored in DT Scalar format. In the above example, the value of **deadline** will be a double containing 20030123000000. See *Date And Time Formats* in the *Language Fundamentals* chapter of the **User Guide** for details on the DT Scalar format.

This example:

invar record=42 \$(1,8) dept (*,2) id # (21,5) wage (*,2) area

will result in:

variable	value	type
dept	ABCDEFGH	character
id	IJ	character
wage	12345	numeric
area	67	numeric

• invarline

Gets input file variable names from a specified line in the input file.

For example:

invarline 1

will get the variable names from the first line of the input file. **invarline** may be used only with delimited ASCII files. In a soft delimited ASCII file, the variable names may be delimited with spaces, commas, or tabs. In a hard delimited ASCII file, the variable names must use the same delimiter as the data. To use **invarline** with a hard delimited ASCII file, call **delimit** to specify the delimiter.

invarline should be used in conjunction with **skip** so that **import** will not attempt to retrieve data from the line in the input file which contains the variable names.

• msym

Specifies the character or string in the input file that is to be interpreted as a missing value.

This example:

msym &

defines the character & as the missing value character.

This example:

msym NA

specifies that each instance of 'NA' in the input file is to be interpreted as a missing value.

The default '.' (dot) will always be interpreted as a missing value unless it is part of a numeric value.

nocheck

Optional, suppresses automatic checking of packed ASCII record length and output data type. The default is to increase the record length by 2 bytes if the second record in a packed file starts with a linefeed, and any files that have explicitly defined character data will be output in double precision regardless of the type specified.

• open

After the conversion, the GAUSS data set is opened for use in GDT:

open

output

The name of the GAUSS data set. A file will be created with the extension .dat.

For example, on Windows

output \research\data\myfile

creates the file myfile.dat on the \research\data directory, or on UNIX,

output /research/data/myfile

creates the file myfile.dat on the /research/data directory.

The command:

output myfile

creates the file in the current working directory.

outtyp

Selects the numerical accuracy of the output file. Use of this command should be dictated by the accuracy of the input data and storage space limitations.

For example:

outtyp D

will write a double precision output file.

outtyp may be set to any of the following:

- D double precision (default)
- F single precision
- I integer

The ranges of the different formats are:

bytes	data type	significant	range
		digits	
2	integer	4	$-32768 \le X \le 32767$
4	single precision	6–7	$8.43 \times 10^{-37} \le X \le 3.37 \times 10^{+38}$
8	double precision	15–16	$4.19 \mathrm{x} 10^{-307} \le X \le 1.67 \mathrm{x} 10^{+308}$

If the output type is integer, the input numbers will be truncated to integers. If your data has more than 6 or 7 significant digits, you should specify **outtyp** as double.

Character and date data require **outtyp d**. **import** automatically selects double precision when character or date data are specified unless you have also specified **nocheck**.

The precision of the storage selected does not affect the accuracy of **GAUSS** calculations using the data. **GAUSS** converts all data to double precision when the file is read.

• outvar

Selects the variables to be placed in the **GAUSS** data set. The **outvar** command needs only the list of variables to be included in the output data set. They can be in any order. If outvar is not used, all of the input variables are written to the output file.

For example:

column	name	data type
1	sex	character
2	age	numeric
3	hiredate	date
4	x001	numeric
5	x003	numeric
6	var01	numeric
7	var02	numeric
8	var03	numeric
9	var04	numeric
10	var05	numeric
11	var06	numeric
12	var07	numeric
13	var08	numeric

invar \$name #age pay \$sex %('YYYY/MO/DD') hiredate #var[1:10] x[005]
outvar sex age hiredate x001 x003 var[1:8]

outvar is not used with packed ASCII files.

• skip

Skips down a specified number of lines from the beginning of the input file before retrieving data.

For example:

skip 5

will skip the first five lines in the input file and begin retrieving data from the sixth line. This command may be used to skip any explanatory notes that are included at the beginning of the ASCII file or to skip lines containing variable names and types. See documentation on the **invarline** and **vartypeline** subcommands for further information on getting variable names and types out of an ASCII file.

typecase

typecase should be used only to create backward compatible data sets which may be used in old programs and applications.

Forces the names of character variables to lower case and the names of numeric variables to uppercase. If **typecase** is specified, the date variable type is not supported. If **typecase** is not specified, the case of each variable name will be preserved.

• vartype

Specifies the types of the input variables.

For example:

vartype \$ # # %('MO/DD/YYYY HH:MI') \$

will specify the types of the input variables as follows:

column	type
1	character
2	numeric
3	numeric
4	date
5	character

If a date variable is specified in a **vartype** statement, then it should be followed by a date format string unless the default is to be used. The default date format string is 'YYYY-MO-DD'. To reset the default date format string for the current **import** job, use the **dateformat** subcommand. A date format string must contain a single delimiter between each element and be enclosed by single quotes. The following date elements are supported:

YYYY	4 digit year
YR	Last two digits of year
MO	Number of month, 1-12
DD	Day of month, 1-31
HH	Hour of day, 0-23
MI	Minute of hour, 00-59
SS	Second of minute, 00-59

If *YR* is specified and the two-digit year is less than or equal to 37, then 2000 will be added to it. Otherwise, 1900 will be added.

It is possible to set both variable names and variable types using **invar**. However, if the variable names are retrieved from the ASCII file with **invarline**, you need to set the variable types using either **vartype** or **vartypeline**. Use **vartype** to set the variable types within your **import** multi-line statement, or **vartypeline** to retrieve the variable types from a specified line in the ASCII file.

The number of variable names must match the number of variable types.

• vartypeline

Retrieves the types of the input variables from a specified line in the input file.

For example:

```
vartypeline 2
```

will retrieve the types of the input variables from the second line of the input ASCII file.

In this case, line 2 of the ASCII file should contain a delimited series of type specifiers: # to indicate numeric data, \$ to indicate character data, and % for date data. A % should be followed by a date format string unless the default is to be used. The default date format string is 'YYYY-MO-DD'. To reset the default date format string for the current **import** job, use the **dateformat** subcommand. A date format string must contain a single delimiter between each element. See **dateformat** for valid date formats.

vartypeline may be used only with delimited ASCII files. In a soft delimited ASCII file, the variable types may be delimited with spaces, commas, or tabs. In a hard delimited ASCII file, the variable types must use the same delimiter as the data.

vartypeline should be used in conjunction with **skip** so that **import** will not attempt to retrieve data from the line in the input file which contains the variable types.

It is possible to set both variable names and variable types using **invar**. However, if the variable names are retrieved from the ASCII file with **invarline**, you need to set the variable types using either **vartype** or **vartypeline**. Use **vartype** to set the variable types within your **import** multi-line statement, or **vartypeline** to retrieve the variable types from a specified line in the ASCII file. The number of variable types found must match the number of variable names indicated by the **invar** or **invarline** command.

2.2.3 Examples

The first example is a soft delimited ASCII file called agex1.asc. The file contains seven columns of ASCII data.

Jan 167.3 822.4 6.34E06 yes 84.3 100.4 Feb 165.8 987.3 5.63E06 no 22.4 65.6 Mar 165.3 842.3 7.34E06 yes 65.4 78.3

The **import** multi-line command is as follows:

(gdt) \setminus

```
1 import ASCII
2 input /gauss/agex1.asc
3 output agex1
4 invar $month #temp pres vol $true #var[02]
5 outvar month true temp pres vol
6 /
```

The output data set will contain the following information:

name	month	true	temp	pres	vol
type	char	char	numeric	numeric	numeric
case 1	Jan	yes	167.3	822.4	6.34e+6
case 2	Feb	no	165.8	987.3	5.63e+6
case 3	Mar	yes	165.3	842.3	7.34e+6

The data set defaults to double precision since no **outtyp** command is specified.

The second example is a packed ASCII file xlod.asc which contains 32-character records.

	AEGDRFCS	Ty02345678	39606315678	390 <cr></cr>	<lf></lf>
	EDJTAJPS	Tn12395863	39980648395	561 <cr></cr>	<lf></lf>
	GWDNADMS	Ty19827845	56597252344	151 <cr></cr>	<lf></lf>
		I			
position	1	10	20	30 31	32

The **import** multi-line command is as follows:

```
( gdt ) \
1 import ASCII
2 input /gauss/dat/xlod.asc
3 output xlod1
4 invar record=32 $(1,3) client[2] zone (*,1) reg #(20,5) zip
5 /
```

name	client1	client2	zone	reg	zip
type	char	char	char	char	numeric
case 1	AEG	DRF	CST	у	60631
case 2	EDJ	TAJ	PST	n	98064
case 3	GWD	NAD	MST	у	59725

The output data set will contain the following information:

The data set is double precision.

The third example is a hard delimited ASCII file called cplx.asc. The file contains six columns of ASCII data:

cvar1,		cvar2,		cvar3,	
456.4,	345.2,	533.2,	-345.5,	524.5,	935.3,
-257.6,	624.3,	639.5,	826.5,	331.4,	376.4,
602.3,	-333.4,	342.1,	816.7,	-452.6,	-690.8

The **import** multi-line command is as follows:

(gdt) \
1 import ASCII
2 input /gauss/cplx.asc
3 output cplx
4 invarline 1
5 skip 1
6 vartype # # #
7 delimit
8 complex
9 /

The output data set will contain the following information:

name	cvar1	cvar2	cvar3
type	numeric	numeric	numeric
case 1	456.4 + 345.2i	533.2 - 345.5i	524.5 + 935.3i
case 2	-257.6 + 624.3i	639.5 + 826.5i	331.4 + 376.4i
case 3	602.3 - 333.4i	342.1 + 816.7i	-452.6 - 690.8i

The data set is double precision.

2.3 Excel File Conversion

Import may also be used to convert Excel files into GAUSS data sets. To execute, enter

import excel

as the first line of a multi-line statement. Each succeeding line should contain a subcommand.

2.3.1 Command Summary

The following subcommands are supported for importing Excel files:

append	Append Excel data to existing GAUSS data set.
datarange	Range of data in the input file, $default = a1$.
datasheet	Sheet in the input file containing the data.
input	The name of the Excel input file.
namerange	Range of input variable names, if any, in the input file.

names	List of input variable names.
namesheet	Sheet in the input file containing input variable names.
open	Open data set after conversion.
output	The name of the GAUSS data set to be created.
overwrite	Overwrite the output GAUSS data set.
translate	Translate Excel special characters to specified values in GAUSS data set.

2.3.2 Example

This example imports a row vector of names starting in cell "a1" in the Excel file, and a matrix of data with upper left starting element in cell "a3". The names and matrix of data are entered into a **GAUSS** data set with file name test1.dat.

```
( gdt ) \
1 import excel
2 input test1.xls
3 namerange a1
4 datarange a3
5 output test1
6 /
```

In the following example, the variable names are stored in a column vector starting in cell "a1" and ending in cell "a6". The data are stored by columns in a block with cell "c1" as the upper left corner and cell "h20" as the lower right corner.

(gdt) \
1 import excel
2 input test2.xls

3 namerange a1:a6 4 datarange c1:h20 5 output test2 6 /

In this example, either the variable names do not exist in the Excel file, or the user chooses not to use them. Default names $X1, X2, \ldots$ are given in the resulting **GAUSS** data set.

```
( gdt ) \
1 import excel
2 input test3.xls
3 datarange a3
4 output test3
5 /
```

Excel Dates

Data that are typed as dates in the Excel file will be transformed to dates in DT format in the **GAUSS** data set.

Special Characters

Special characters in the Excel file can be transformed to specified numerical values in the **GAUSS** data set. The special characters are

empty #N/A #VALUE! #DIV/0! #NAME? #REF! #NUM! #NULL! #ERR

By default they are all converted to **GAUSS** missing values. If a numeric value is wanted, use the **translate** command, specifying both the special character and the numeric value. For example:

translate #N/A = 999

translates all instances of #N/A to 999 in the GAUSS data set.

2.3.3 Commands

A detailed explanation of each subcommand follows.

append

Instructs **import** to append the Excel data to an existing data file:

append

No assumptions are made regarding the format of the existing file. You should make certain that the number, order and type of data converted match the existing file. **import** creates v96 format data files, so it will only append to v96 format data files.

• datarange

Specifies the cell range of the data in the Excel file:

datarange a1:c100

If the data is in consecutive cells in columns, only the upper left cell needs to be specified:

datarange a1

• datasheet

Specifies the sheet of the data in the Excel file:

datasheet 2

The default is 1.

• input

Specifies the file name of the Excel file to be converted. The full path name can be used in the file specification.

For example, the command:

input data.raw

will expect an Excel data file in the current working directory.

The command:

input \research\data\myfile.asc

specifies a file to be located in the \research\data subdirectory.

• namerange

Specifies the cell range of the names of the columns of the data in the Excel file, if any:

When the **namerange** option is specified as a single cell, the names are assumed to be distributed in a row with names in consecutive cells. Suppose there are 6 columns of data and thus 6 names in the Excel file. Then the option

namerange al

is equivalent to

namerange a1:f1

If the names are listed in a column rather than a row, then the entire range must be specified. For example:

namerange a1:a6

If names do not exist in the Excel file nor are specified by the **names** command, default names are given: $X1, X2, \ldots, X_k$.

names

If the Excel file does not contain the names of the columns of the data, they can be specified with this command:

names age, sex, pay

If names are neither specified with this command nor exist in the Excel file, default names are given: $X1, X2, ..., X_k$.

namesheet

Specifies the sheet of the variable names in the Excel file:

namesheet 2

The default is 1.

• open

Opens the GAUSS dataset in GDT after creation:

open

• output

The name of the GAUSS data set. A file will be created with the extension .dat.

For example:

output \research\data\myfile

creates the file myfile.dat on the \research\data directory.

The command:

output myfile

creates the file in the current working directory.

• overwrite

This command is used to specify that the output **GAUSS** data set will replace a current **GAUSS** data set with the same name if it exists:

overwrite

• translate

This command specifies that certain special characters in the Excel file are translated to given values in the **GAUSS** data set. By default these special characters are translated to **GAUSS** missing values.

The following are the special characters:

empty #N/A #VALUE! #DIV/0! #NAME? #REF! #NUM! #NULL!

#ERR

For example, to translate all instances of #ERR to 999, enter

translate #ERR = 999

A separate **translate** command is required for each translation. All special characters not associated with a **translate** command are translated to **GAUSS** missing values.

Export 3

Import

3.1 Overview

export is a multi-line **GDT** command that converts **GAUSS** data sets into data files of other types. It currently supports conversion to both ASCII and Excel files.

3.2 ASCII File Conversion

Export may be used to convert an active GAUSS data set into a delimited ASCII file. To execute, enter

export ASCII

as the first line of a multi-line statement. Each succeeding line should contain a subcommand.

3.2.1 Command Summary

The following subcommands are supported for exporting ASCII files:

append	Append to already existing output file.		
dateformat	Specify format for date data.		
drop	Write all variables except those specified.		
finaldelim	Specify delimiter to be written at the end of the file.		
keep	Write only specified variables.		
noquote	Do not quote character and date data.		
obsdelim	Specify delimiter to be written between observations.		
output	The name of the ASCII data file to write.		
overwrite	Overwrite output file if it already exists.		
vardelim	Specify delimiter to be written between variables.		
writevarnames	Write variable names to output file.		
writevartypes	Write variable types to output file.		

3.2.2 Commands

A detailed explanation of each subcommand follows.

• append

Instructs **export** to append the converted data to an existing ASCII file:

append

No assumptions are made regarding the format of the existing file. You should make certain that the number, order and type of data converted match the existing file.

dateformat

Specifies the format in which date data should be written to the output file. The format is as follows:

dateformat default_date_format date_format var_name...

Each *var_name* that is directly specified will be written in the ASCII file according to the *date_format* immediately preceding. Any date variables in the data set that are not directly specified will be written according to the *default_date_format*.

For example, when exporting a data set containing the following variables:

column	name	data type
1	Pname	character
2	Edate	date
3	Start	date
4	End	date
5	Elapsed	date

the command:

dateformat 'HH:MI' 'MO/DD/YYYY' Edate

specifies that **Edate** is to be written using the format 'MO/DD/YYYY', and **Start**, **End**, and **Elapsed** using the format 'HH:MI'.

A date format string must contain a single delimiter between each element and must be enclosed by single quotes. The following date elements are supported:

YYYY	4 digit year
YR	Last two digits of year
MO	Number of month, 1-12
DD	Day of month, 1-31
HH	Hour of day, 0-23
MI	Minute of hour, 00-59
SS	Second of minute, 00-59

If no date format is specified with the **dateformat** command, any date data encountered in the data set will be written according to the default for importing and exporting date data. The default date format is 'YYYY-MO-DD'.

• drop

Specifies variables that are NOT to be written to the output file. For example, when converting a data set containing three variables, x1, x2 and x3, to an ASCII file, the command:

specifies that only variable x3 be written to the output file.

• finaldelim

Specifies the delimiter to be written after the final observation in the output ASCII file.

For example:

```
finaldelim '|'
```

specifies that the final observation in the output file be followed by a vertical bar.

• keep

Specifies variables to be written to the output file. For example, when converting a data set containing three variables, x1, x2 and x3, to an ASCII file, the command:

keep x2,x3

specifies that only variables x^2 and x^3 be written to the ASCII file.

noquote

Instructs **export** to write character and date data to the output ASCII file without quotes:

noquote

By default, character and date data are enclosed by double quotes in the output file.

obsdelim

Specifies the delimiter to be written between each observation in the output ASCII file.

To specify the delimiter to be written after the final observation in the ASCII file, use **finaldelim**.

For example:

```
obsdelim ','
```

specifies that each observation in the output file except the last be followed by a comma.

• output

GAUSS Data Tool

The name of the output ASCII file.

For example, on Windows

output \research\data\myfile.asc

creates the file myfile.asc on the \research\data directory, or on UNIX,

output /research/data/myfile.asc

creates the file myfile.asc on the /research/data directory.

The command:

output myfile.asc

creates the file in the current working directory.

• overwrite

Overwrites the output ASCII file if it already exists:

overwrite

By default, export will error out if the specified output file exists.

• vardelim

Specifies the delimiter to be written between each variable within an observation in the output ASCII file.

To specify the delimiter to be written between observations, use **obsdelim**.

For example:

vardelim ', '

specifies that a comma and a space be written between each variable within an observation in the output file.

• writevarnames

Writes the names of the variables in the output file before the data:

writevarnames

The variable names will be enclosed by double quotes unless **noquote** is specified, and they will be delimited in the same way as the data that follows.

• writevartypes

Writes the types of the variables in the output file before the data:

writevartypes

The variable types will be enclosed by double quotes unless **noquote** is specified, and they will be delimited in the same way as the data that follows. A date type specifier, %, will be followed by the corresponding date format string.

3.2.3 Examples

The first example is a **GAUSS** data set called **einfo.dat**, which has five variables and contains the following data:

GAUSS Data Tool

varname	Ename	bdate	age	pay	hiredate
type	char	date	numeric	numeric	date
case 1	Sue	19710421000000	33	60000	20010115000000
case 2	Tom	19570905000000	47	90000	19981015000000
case 3	James	19641230000000	40	65000	19950401000000
case 4	John	19740528000000	30	58000	19970701000000

The following **export** multi-line command:

```
( gdt . einfo ) \
1 export ASCII
2 output /gauss/einfo.asc
3 writevarnames
4 writevartypes
5 dateformat 'MO/DD/YR'
6 vardelim ', '
7 obsdelim ,
8 /
```

will produce the output ASCII file einfo.asc on the gauss directory, which will contain:

```
"Ename", "bdate", "age", "pay", "hiredate",
"$", "%('MO/DD/YR')", "#", "#", "%('MO/DD/YR')",
"Sue", "04/21/71", 33, 60000, "01/15/01",
"Tom", "09/05/57", 47, 90000, "10/15/98",
"James", "12/30/64", 40, 65000, "04/01/95",
"John", "05/28/74", 30, 58000, "07/01/97"
```

The second example converts a **GAUSS** data set called test1.dat, which has four variables and contains the following data:

Export

varname	Month	X1	X2	X3
type	char	numeric	numeric	numeric
case 1	JAN	162384	105.32	1546
case 2	FEB	123643	462.15	3628
case 3	MAR	102738	362.9	9361

The following **export** multi-line command:

```
( gdt . test1 ) \
1 export ASCII
2 output /gauss/mdata.asc
3 writevarnames
4 writevartypes
5 drop x2
6 noquote
7 vardelim |
8 /
```

will produce the output ASCII file mdata.asc on the gauss directory, which will contain:

```
Month|X1|X3
$|#|#
JAN|162384|1546
FEB|123643|3628
MAR|102738|9361
```

3.3 Excel File Conversion

Export may be used to convert GAUSS data sets into Excel files. To execute, enter

export excel

as the first line of a multi-line statement. Each succeeding line should contain a subcommand.

3.3.1 Command Summary

The following subcommands are supported for exporting Excel files:

datarange	Range of data in the output file, $default = a1$.
datasheet	Sheet in the output file for the data.
deletefile	Delete existing output file.
drop	Write all variables except those specified.
keep	Write only specified variables.
namerange	Range of names, if to be written to Excel file.
namesheet	Sheet in the output file of names.
output	The name of the output Excel file.
translate	Translate specified GAUSS numbers into Excel special characters.
update	Update existing output file.

Names

If **namerange** is not set, names will not be written to the Excel file. If **namerange** is set to a single cell, names will be written row-wise. To write names to a column, beginning and ending cells must be specified, e.g., "A1:A5".

Special Characters

Specified numbers in the GAUSS data set can be written as special characters in the Excel data set. The special characters are

empty #N/A #VALUE! #DIV/0! #NAME? #REF! #NUM! #NULL! #ERR

By default, GAUSS missing values will be written as empty cells.

3.3.2 Example

This example exports the data in a **GAUSS** data set called test.dat into the first sheet of an Excel file where the upper left element of the data goes into cell "a3" and the names are entered row-wise starting in cell "a1".

(gdt . test) \
1 export excel
2 output test.xls

3 namerange a1 4 datarange a3 5 /

In the following example, the names are left out of the Excel file, and **GAUSS** missing values in the data are translated to a special Excel character:

```
( gdt . test ) \
1 export excel
2 output test.xls
3 datarange a3
4 translate . = #N/A
5 /
```

3.3.3 Commands

A detailed explanation of each subcommand follows.

• datarange

Specifies the range for the data in the output Excel file. Only the upper left cell is required:

```
datarange c4
```

The default is cell a1;

datasheet

Specifies the sheet of the data in the Excel file:

datasheet 2

The default is 1.

• deletefile

Deletes the output Excel file if it already exists before exporting:

deletefile

By default, export will error out if the specified output file exists.

• drop

Specifies columns in the GAUSS data set to be excluded from the output Excel file. For example,

drop age, pay

• keep

Specifies columns in the GAUSS data set to be included in the output Excel file.

For example,

keep age, pay

If neither **keep** nor **drop** commands are entered, all columns are included in the Excel file.

• namerange

Specifies the cell range in the Excel file for the names. If there is not a **namerange** command, the names will not be entered into the Excel file.

If a single cell is specified, the names are entered in consecutive cells row-wise. Thus

namerange a1

for 3 names is equivalent to

namerange a1:c1

To enter the names in a column, the entire range must be specified:

namerange a1:a3

• namesheet

Specifies the sheet of the variable names in the Excel file:

namesheet 2

The default is 1.

• output

The name of the output Excel file. A file will be created with the extension .xls.

For example

output \research\data\myfile

creates the file myfile.xls on the *research**data* directory.

The command:

output myfile

creates the file in the current working directory.

• translate

This command is used to translate specified values in the **GAUSS** data set into special characters in the Excel file. By default **GAUSS** missing values are translated into empty cells in the Excel file.

The following are the special characters:

empty #N/A #VALUE! #DIV/0! #NAME? #REF! #NUM! #NULL! #ERR

For example, to translate all instances of 999 in the **GAUSS** data set into the special character #ERR, enter

translate 999 = #ERR

A separate **translate** command is required for each translation.

• update

Instructs **export** to update an existing Excel file with the specified data translation:

update

This subcommand allows you to overwrite a part of an existing Excel file or append to an Excel file. No assumptions are made regarding the format of the existing file.

Statement Reference

add

- PURPOSE Creates a new data set variable.
 - FORMAT **add** [[vtype]] newvar = expression
 - add [[vtype]] newvar1, newvar2, ...

Valid vtypes are:

- # numeric (default)
- \$ character
- % date

allops

OUTPUT	A $nobs \times 1$ variable is added to the active data set, where <i>nobs</i> is the number of observations in the data set.							
REMARKS		This is a transformation expression and all operators are dot (element by element) operators unless this feature has been turned off using allops .						
		sent, a vector of zeros is added to the data set, a NULL string for character variables and a e variables.						
		If an expression is given, it must produce a vector of length equal to the number of observations in the active data set.						
CODE		add # agecat = age >= 21 and age < 65 add \$ sex = "Male" * (nsex == 1) + "Female" * (nsex == 2)						
	The example above creates <i>agecat</i> with a value of 1 where <i>age</i> $>= 21$ and <i>age</i> < 65 , otherwise, <i>agecat</i> is created with a value of 0. Then the character variable <i>sex</i> is created with a value of "Male" where <i>nsex</i> is 1 or a value of "Female" where <i>nsex</i> is 2.							
EXAMPLE	(gdt) open linear (gdt linear) lv							
	> linear	3 vars, 100 obs, /data/linear.dat						
	Y	numeric						
	X1	numeric						
	X2	numeric						
	(gdt linear) add ex2 =	gdt linear) add $ex2 = exp(x2)$						
	(gdt * linear) lv							
	> * linear	4 vars, 100 obs, /data/linear.dat						
	Y	numeric						
	X1	numeric						
	X2	numeric						
	* ex2	numeric						
SEE ALSO	create							

- PURPOSE Turns off interpretation of scalar-returning operators as element by element operators.
 - FORMAT allops
- REMARKS Non-dot operators in a transformation expression will be interpreted as scalar-returning operators and dot operators will be interpreted as element by element operators.

Code inside of procedures is not affected by this setting.

For more information, refer to *Scalar and Element by Element Operations* (Section 1.4) and *Element by Element Operators* in the **GAUSS Users Guide**.

CODE allops

EXAMPLE	(gdt .) open tobit (gdt . tobit) lv						
	> tobit	4 vars,	100 obs,	/data/example/tobit.dat			
	Y	numer	ic				
	CNST	numer					
	X1	numeric					
	X2	numeric					
	(gdt . tobit) allops						
	All operators behave normally in transformations						
	(gdt # tobit) add y2 = y < 20						
	Expression returns wrong size value						
	Returns 1x1						
	Should be 100x1						

In this example, *y*2 will be a scalar because **allops** is in effect. An

cat

error message is issued because *y*² does not have the correct number of rows (observations).

SEE ALSO dotops

cat	
PURPOSE	Combines all variables in a data set into a matrix.
FORMAT	cat matrix_name [[name_vector]]
OUTPUT	$N \times K$ matrix with columns corresponding to variables.
REMARKS	Creates a matrix in the data set workspace containing all the variables in the data set in the same order as the lv command variable list.
	If <i>name_vector</i> is specified, a $K \times 1$ string array is created containing the names of the variables.
	Use this command to combine the individual vectors into a single matrix to facilitate operations that can be done more easily with matrix operations.
	Use split to move the data from the matrix back into the individual vectors.
CODE	cat max0 vname
EXAMPLE	This example standardizes the variables in a data set.
(gdt maxfact) cat max0

cd

<pre>(gdt maxfact) g max0 = (max0 - meanc(max0)') ./ stdc(max0)' Using maxfact workspace (gdt maxfact) stats > maxfact</pre>							
Variable	Mean	Std Dev	Variance	Minimum	Maximum	Valid	Missing
Y1 0.0275 1.0706 1.1461 -3.1796 2.8096 100 Y2 0.0041 0.8206 0.6734 -1.4813 2.7042 100 Y3 0.1155 0.9598 0.9212 -1.9176 3.8984 100 Y4 0.1058 0.8382 0.7025 -2.1307 2.1470 100 (gdt maxfact) split max0 (gdt * maxfact) stats > * maxfact 4 vars, 100 obs /data/maxfact.dat						0	
Variable			Variance		Maximum	Valid	Missing
* Y1 * Y2 - * Y3 - * Y4 - (gdt * max	0.0000 -0.0000 -0.0000 -0.0000	1.0000 1.0000 1.0000	1.0000 1.0000 1.0000	-2.9958 -1.8101 -2.1182	3.2904 3.9413	100 100	0 0

The data set does not change until the **split** command is executed, as can be seen by the output of the two **stat** commands in the above example.

```
SEE ALSO split
```

cd

PURPOSE Changes the working directory.

FORMAT **cd** *file_path*

cleanup

REMARKS The directory is changed to the directory specified.

CODE cd /file/path

cleanup

PURPOSE Removes from a workspace all symbols that are not data set variables.

FORMAT cleanup

- REMARKS When GDT opens a data set, the data are loaded into a workspace as individual vectors. As certain commands are executed, extraneous symbols, such as data, procedures, and new variables, are left in the workspace. These extraneous symbols can be removed with the cleanup command, which deletes all symbols except variables that are part of the opened data set, or created with the **add** or **code** statements.
 - CODE cleanup

close

- PURPOSE Closes an open data set.
 - FORMAT **close** [[handle, handle, ...]]
- **REMARKS** If a *handle* is not specified, the active data set is closed.

If there are uncommitted changes, the user will be prompted to save or discard the changes or cancel the close.

CODE close

- EXAMPLE (gdt freqdata) close (gdt)
- SEE ALSO open, use, nouse

code

PURPOSE	Creates a new variable with discrete values.
FORMAT	<pre>code [[vtype]] newvarname with</pre>
	value1 for expression1,
	value2 for expression2,
	÷
	valueN for expressionN
	<pre>[[default default_value_expression]]</pre>
	Valid vtypes are:

- # numeric (default)
- \$ character
- % date

REMARKS		<i>value</i> in the for clause and <i>default</i> must be a scalar value or a scalar-returning expression.						
	0) result assigned	The <i>expression</i> in the for clause must return a true or false (non-zero or 0) result. If the expression returns true (non-zero), the new variable is assigned the <i>value</i> in that for clause, otherwise, the new variable will be assigned the <i>default</i> value if specified or a value of 0.						
	procedu	The code statement syntax requires multiple-line entries. The procedure for entering and working in multi-line mode is described in <i>User Interfaces</i> (Section 1.3).						
		Commas are required between each for expression; no comma is allowed after the last for expression.						
CODE	1 2 3 4	<pre># agecat wit for age < 21 for age >= 2 for age >= 3 for age >= 4 efault 5</pre>	, 1 and age < 1 and age <	40,				
EXAMPLE	(gdt garc	h) report fre	q					
		ESSED BY THIS						
		100 cases were kept out of 100. 0 deleted because of missing values.						
	Y		2.42655	* ****				
	Valid	100.0000		*****				
	Missing	0.0000		****				
	Mean	0.9821		****				
	Std Dev	0.6008		****				
	Variance	0.3610		****				
	Mode	-1.0168		*				
	Minimum	-1.0168		*				
	Maximum	2.4265	-1.01679	**				

```
Total N 100
 -----
(gdt garch ) \
> code newy with
> 1 for y < -.5,
> 2 for y \ge -.5 and y < .5,
> 3 for y >= .5
> /
(gdt * garch ) \setminus
> report freq
> use newy
> /
CASES PROCESSED BY THIS PROCEDURE:
  100 cases were kept out of 100.
  0 deleted because of missing values.
                          3.00000 |***************
newy
Valid
         100.0000
Missing
           0.0000
                                  | * * *
Mean
           2.8200
Std Dev
           0.4579
Variance
            0.2097
Mode
            3.0000
Minimum
            1.0000
Maximum
                         1.00000 |*
            3.0000
           Percents
                                       Percents
Value Count Cell
                    Cum Value Count Cell
                                                Cum
                    _____
        -----
                                   _____
   1
        3 3.00
                    3.00
                             3 85 85.00 100.00
   2 12 12.00 15.00
   _____
Total N 100
```

(gdt * garch)

SEE ALSO recode

commit

- PURPOSE Saves current or specified data set changes to the disk.
 - FORMAT **commit** [[handle]]
- **REMARKS** If *handle* is not specified, the active data set is committed.

Executing a **commit** makes modifications to the data set permanent.

- CODE commit simdata
- EXAMPLE (gdt) open maxfact
 (gdt maxfact) add y5 = y1 + y2
 (gdt * maxfact) commit
 5 variables and 100 observations written to /data/maxfact.dat
 (gdt maxfact)
- SEE ALSO rollback

сору

PURPOSE Copies variables to or from the active data set.

FORMAT copy [[var1, var2, ...]] from handle

copy [[var1, var2, ...]] to handle

REMARKS If no variables are specified, all variables in the source are copied.

CODE copy age from freqdata

copy X1 to simdata

EXAMPLE (gdt .) open examples/maxsimeq (gdt . maxsimeq) open examples/tobit (gdt . tobit) copy y2 from maxsimeq 1 variables copied (gdt . * tobit) lv > * tobit 5 vars, 100 obs, /gauss/examples/tobit.dat Y numeric CNST numeric X1 numeric X2 numeric * Y2 numeric (gdt . * tobit) copy cnst to maxsimeq 1 variables copied (gdt . * tobit) use maxsimeq (gdt . * maxsimeq) lv > * maxsimeg 5 vars, 100 obs, /gauss/examples/maxsimeq.dat Y1 numeric Y2 numeric X1 numeric X2 numeric * CNST numeric (gdt . * maxsimeq)

create

PURPOSE Creates an empty data set.

create

FORMAT	<pre>create data_set_name</pre>					
OUTPUT	A data set with no variables is added to the GAUSS session.					
REMARKS	If no arguments are included, all open d	If no arguments are included, all open data sets are listed.				
	Use the add or code statements to creat	Use the add or code statements to create variables in the data set.				
	-	The data set is written to disk only when the commit statement is executed; the data set is written as a .dat file.				
		The first variable added to the new data set establishes the number of observations and subsequently added variables must have the same number of observations.				
CODE	create newdat					
EXAMPLE	<pre>(gdt .) create newdat (gdt .) add y = rndn(100,1) (gdt . * newdat) lv > * newdat</pre>	, 100 obs, newdat.dat eric				
	(gdt . * newdat) report freq					
	CASES PROCESSED BY THIS PROCEDURE:					
	100 cases were kept out of 100. 0 deleted because of missing values.					
	у 3.06419	** *				
	Valid 100.0000	****				
	Missing 0.0000	****				
	Mean -0.0683	************************************				
	Std Dev 1.1759 Variance 1.3826	*****				
		1				

Mode -3.2408 |** Minimum -3.2408 |*** Maximum 3.0642 -3.24079 |* Total N 100 (gdt . * newdat) commit (gdt . newdat)

SEE ALSO add

delete

PURPOSE	Deletes observations based on an expression.			
FORMAT	delete where expression			
CODE	delete where age < 21			
EXAMPLE	(gdt maxfact) delete where y5 < -3.9 Deleted 1 rows from maxfact, 99 are left (gdt * maxfact)			

dotops

PURPOSE Turns on interpretation of scalar-returning operators as element by element operators.

drop

FORMAT	dotops
REMARKS	Non-dot (scalar-returning) operators in a transformation expression will be interpreted as dot operators (element by element).
	Code inside of procedures is not affected by this setting.
	For more information, refer to <i>Scalar and Element by Element</i> <i>Operations</i> (Section 1.4) and <i>Element by Element Operators</i> in the GAUSS Users Guide .
CODE	dotops
EXAMPLE	<pre>(gdt # tobit) dotops Operators are dot operators in transformations (gdt . tobit) add y2 = y < 20 (gdt . * tobit) add y3 = y .< 20 (gdt . * tobit)</pre>
	In the example above, y^2 and y^3 will be identical.
SEE ALSO	

drop

- PURPOSE Drops variables from a data set.
 - FORMAT **drop** var1[[, var2, ...]]
 - CODE drop x1,x2
- EXAMPLE (gdt maxfact) drop y5, y6

2 variables dropped
(gdt * maxfact)

SEE ALSO keep

export

- PURPOSE Translates a GAUSS data set to a data file of a different format.
 - FORMAT **export** *export_type*
- REMARKS The export statement syntax requires multiple line entries. Procedures for entering multiple line entries are described in *User Interfaces* (Section 1.3).

For available export types enter:

help export

For information on a particular export type enter:

help export export_type

For more discussion see Section 3.1.

CODE export ascii

EXAMPLE (gdt freqdata) \ 1 export ascii 2 output fdata.asc

Statement Reference 3 keep age,pay,sex
4 writevarnames
5 /

frename

PURPOSE	Changes the file name associated with the active data set.
FORMAT	<pre>frename new_data_set_name</pre>
REMARKS	The active data set is saved to disk under <i>new_data_set_name</i> . The original data set file is left unchanged as of the last commit .
	To change the name of a data set file, use the operating system command for renaming files.
CODE	frename lgtsim
EXAMPLE	<pre>(gdt maxfact) frename /data/factor 4 variables and 100 observations written to /data/factor.dat (gdt factor) See vrename, remove, recover</pre>

PURPOSE Executes GAUSS commands and statements in the active workspace.

FORMAT g gauss_command_or_statement

g

REMARKS Separate multiple statements with semi-colons (;).

allops and **dotops** do not effect code executed with the **g** statement.

EXAMPLE (gdt .) open cmlfact (gdt . cmlfact) cat fdata (gdt . cmlfact) g r = corrx(fdata) Using cmlfact workspace (gdt . cmlfact) g print r Using cmlfact workspace

1.0000000	0.66830903	0.32650504	0.21293355
0.66830903	1.0000000	0.30232712	0.24065234
0.32650504	0.30232712	1.0000000	0.59052208
0.21293355	0.24065234	0.59052208	1.0000000

```
( gdt . cmlfact ) g { p,v,a } = princomp(fdata,4)
Using cmlfact workspace
( gdt . cmlfact ) g print v
Using cmlfact workspace
```

```
0.55622722
0.27164763
0.094103380
0.078021774
(gdt.cmlfact)
```

SEE ALSO cat, split

import

PURPOSE Translates a data file to a GAUSS data set.

FORMAT **import** *import_type*

REMARKS The import statement syntax requires multiple line entries. Procedures for entering multiple line entries are described in *User Interfaces* (Section 1.3).

For available import types enter:

help import

For information on a particular import type enter:

help import import_type

For more discussion see Section 2.1.

CODE import ascii

EXAMPLE (gdt) \

1 import ascii
2 input mydata.asc
3 output mydata
4 invarline 1
5 vartypeline 2
6 skip 2
7 /

impute

PURPOSE Imputes missing data.

FORMAT impute impute_method

REMARKS The impute statement syntax requires multiple line entries. The procedure for entering multiple line entries is described in *User Interfaces* (Section 1.3).

For available imputation methods enter:

help impute

For information on a particular method enter:

help impute impute_method

CODE	impute	ems							
EXAMPLE	(gdt .) (gdt . fr	-	-						
	<pre>> freqda</pre>	 ta	4 vars,	400 obs	/gauss/e	examples/f	freqdat	======= a.dat	Ref
	Variable	Mean	Std Dev	Variance	Minimum	Maximum	Valid	Missing	Reference
	AGE PAY	5.6784 1.9675	2.9932 0.8019		1.0000	10.0000 3.0000		=	ice
	sex WT	1.4699	0.3007	0.0904	1.0000	1.9900	400	0	
	(gdt .fr	eqdata 🕽) impute e	ems					
	will conti However, i	nue with t may no ta model	n this var ot conform L which re	y be categor riable codec to the ass equires Norm	l to a seq sumptions	luence,			
	======================================	======= ta 4	 1 vars,	400 obs	/gauss/ex	amples/fr	reqdata	======= .dat	
	Variable	Mean	Std Dev	Variance	Minimum	Maximum	Valid	Missing	

Statement

* AGE 5.6785 2.9858 8.9147 1.0000 10.0000 400 0 * PAY 1.9675 0.8019 0.6431 1.0000 3.0000 400 0 * sex 1.3850 0.4872 0.2374 1.0000 2.0000 400 0 * WT 1.4699 0.3007 0.0904 1.0000 1.9900 400 0 (gdt . * freqdata)

keep

PURPOSE	Drops all variables except those listed.			
FORMAT	keep variable1[[, variable2,]]			
CODE	keep y1, y2			
EXAMPLE	<pre>(gdt factor) lv > factor 4 vars, 100 obs, /data/factor.dat Y1 numeric Y2 numeric Y3 numeric Y4 numeric (gdt factor) keep y1,y2 2 variables kept</pre>			
	<pre>(gdt * factor) lv > factor 2 vars, 100 obs, /data/factor.dat Y1 numeric Y2 numeric</pre>			

ld

FORMAT	ld <i>file_pa</i>	th			
REMARKS	Files in the	e current	directory	are displa	ayed if <i>file_path</i> is not specified.
CODE	ld /data	/examp]	les		
EXAMPLE	(gdt facto	c) 1d			
				100 -h-	(data (namah dat
	garch	-			, /data/garch.dat
	linear	free,	5 vars,	100 obs	, /data/linear.dat
	logit2	free,	3 vars,	1000 obs	, /data/logit2.dat
	maxfact	free,	4 vars,	100 obs	, /data/maxfact.dat
	sci	free.	23 vars,	154 obs	, /data/sci.dat
	(gdt facto	r)	,		

Lists data sets that are on disk.

	S
Л	~ ~ ~
Ð	
- -	2
O	-
<u> </u>	Ð
	<u> </u>
Ð	-
-	1
_	Ð
0	-
Ä	_

PURPOSE	Lists variables in the active or specified data set.			
FORMAT	lv [[handle]]			
REMARKS	The variables are listed in the order they appear in the data set.			
CODE	lv			
	lv histdata			
EXAMPLE	<pre>(gdt freqdata) lv > freqdata 4 vars, 400 obs, /data/freqdata.dat AGE numeric PAY numeric</pre>			

PURPOSE

	sex			character
	WT			numeric
(gdt	freqdata)	

merge

PURPOSE	Merges data sets on a key variable or list of key variables.
FORMAT	<pre>merge from handle on keyvar1, keyvar2, [[variables var1, var2,]]</pre>
REMARKS	The active data set is modified by the merge while the other is left unchanged.
	Data sets to be merged must have at least one common key variable between them. Only observations that match on key variables in both data sets are included in the merge. All other observations are deleted from the active data set.
	Key variables in both data sets must be sorted unique before merging.
	If no variables are specified, all variables from the <i>handle</i> not in the key variable list are merged into the active data set, otherwise, only the specified variables from the <i>handle</i> are merged.
	Merged variables with duplicate names in both the <i>handle</i> and active data set are renamed.
CODE	merge from empdata on empid variables department, hiredate, position
EXAMPLE	(gdt .) open sim1

```
(gdt . sim1 ) lv
> sim1
                                            100 obs, /data/sim1.dat
                                2 vars,
                                    numeric
  ky
  y1
                                    numeric
(gdt . sim1 ) open sim2
(gdt . sim2 ) lv
> sim2
                                            100 obs, /data/sim2.dat
                                2 vars,
 ky
                                    numeric
                                    numeric
 y2
(gdt . sim2 ) merge from sim1 on ky
( gdt . * sim2 ) lv
> * sim2
                                 3 vars.
                                             100 obs, /data/sim2.dat
* ky
                                    numeric
* y2
                                    numeric
* y1
                                    numeric
( gdt . * sim2 )
```

SEE ALSO copy, sort, stack

model

- PURPOSE Creates a data set from a model simulation.
 - FORMAT **model** model_name
 - OUTPUT A new data set containing simulated data.
- REMARKS The model statement syntax requires multiple line entries. Procedures for entering multiple line entries are described in *User Interfaces* (Section 1.3).

For available models enter:

help model

For information on a particular model enter:

help model model_name

CODE model probit

(gdt)∖ 1 model arima 2 file test

EXAMPLE

3 depvar Y 4 indvar X1,X2 5 vcx 1,.4,1 6 ar .3,.1 7 ma .2 8 normal 1.5 9 open 10 / (gdt . test) report freq CASES PROCESSED BY THIS PROCEDURE: 100 cases were kept out of 100. 0 deleted because of missing values. Y 3.92054 |* | * * * | * * * * * * * Valid 100.0000 | * * * * * * Missing 0.0000 **** Mean 0.9487 ***** Std Dev 1.0865 | * * * * * * * * * Variance 1.1804 ****** Mode -1.6957 | * * Minimum -1.6957-1.69574 |***** Maximum 3.9205

X1		2.77424	
X1		2.77424	
			**
			*
Valid	100.0000		*****
Missing	0.0000		****
Mean	0.1678		****
Std Dev	0.9554		****
Variance	0.9128		****
Mode	-1.4980		****
Minimum	-1.4980		****
Maximum	2.7742	-1.49800	****
Total N	100		
X2		2.88571	•
			*
Valid	100.0000		*****
Missing	0.0000		*****
Mean	0.0246		****
Std Dev	0.9947		****
Variance	0.9894		****
Mode	-2.1527		****
Minimum	-2.1527		****
Maximum	2.8857	-2.15270	****
Total N	100		
(gdt . tes	t)		

nouse

PURPOSE	Makes the active data set not active.
FORMAT	nouse
REMARKS	It is possible for no open data sets to be active.
CODE	nouse freqdata
EXAMPLE	(gdt freqdata) nouse freqdata (gdt)
SEE ALSO	use, open, close

open

- PURPOSE Loads a data set into a workspace and makes it the active data set.
 - FORMAT **open** *data_set_name*
- **REMARKS** Each open data set has its own workspace. The data are loaded into the workspace as K Nx1 vectors. Vector names are the same as the data set variable names.

If no arguments are included, a list of open data sets is displayed on the screen.

CODE open examples/freqdata

SEE ALSO close, use, nouse

- FORMAT **p** [[numobs]] [[var]]
- REMARKS If no arguments are specified, the first *numobs* observations of each variable in the data set are displayed on the screen. The default value of *numobs* is 50. To change the default value, enter the *numobs* parameter with no variable name. The default will remain changed until **GDT** is restarted.

If a variable name is specified, the first *numobs* observations of the specified variable are displayed, and options are given for viewing other observations within that variable.

CODE p 100 age

EXAMPLE	(gdt tobit) p 10 (gdt tobit) p
	Υ =
	[1:5]0.19122822-0.52539158-0.155408380-1.2125193[6:10]00.310774571.1137943-0.936159740.80979624
	CNST =
	[1:10] 1 1 1 1 1 1 1 1 1 1
	X1 =

р

[1:5] 0.59209035 0.25336661 0.88820146 -0.85628518 0.25278613 [6:10] 0.32553164 -0.036312038 0.94893974 -1.3409896 -0.22219151 X2 = [1:5] -0.35181439 0.025950747 1.7658545 1.0476031 -0.78446166 [6:10] -0.12405032 -0.022460097 0.37790726 -0.79498798 -0.24560567 (gdt tobit) p 25 y Y = [1:5] 0.19122822 -0.52539158 -0.15540838 0 -1.2125193[6:10] 0 0.31077457 1.1137943 -0.93615974 0.80979624 [11:15 -0.79397375 0.56180099 -0.20987604 0.71051733 -0.68155363 [16:20] 0.98908776 1.0933305 0.04909111 -0.92224655 1.4741197 [21:25] -1.0520466 1.3088757 2.41852 0.13847887 2.1946464 (Next | Previous | Top | Bottom | ### | Show ### | Help | Quit) [N] n Y = [26:30] 0.22283408 -0.35802955 0.078518682 -0.30831094 -0.28662837 [31:35] -0.63163611 0 -0.16819537 1.0455784 0.28637601 [36:40] -0.19024424 0.19664649 -0.97867385 0.27319029 0.39976644 [41:45] 0.60695266 0.10849636 0.038987486 1.044837 0 [46:50] 0.52982032 -0.92003283 -0.11145973 -0.69712074 0.63632036 (Next | Previous | Top | Bottom | ### | Show ### | Help | Quit) [N] q

(gdt tobit)

pwd

PURPOSE Shows the current directory.

FORMAT pwd

CODE pwd

EXAMPLE (gdt.tobit) pwd Current directory:/data/examples (gdt.tobit)

q, quit

- PURPOSE Exits GDT
 - FORMAT q

quit

CODE q

quit

EXAMPLE (gdt.tobit)q (/data/example)%

(gdt . tobit) quit
(/data/example)%

Statement Reference

recode

PURPOSE Recodes a variable to discrete values.

FORMAT **recode** [[vtype]] varname with

value1 for expression,

value2 **for** expression,

÷

valueN for expression

Valid vtypes are:

- # numeric
- \$ character
- % date

REMARKS If *vtype* is not specified, the type of the variable is unchanged.

value in the **for** clause must be a scalar value or a scalar-returning expression.

The *expression* in the **for** clause must return a true or false (non-zero or 0) result; if the expression returns true (non-zero), the variable is assigned the *value* in that **for** clause, otherwise, the variable value remains unchanged.

The **recode** statement syntax requires multiple-line entries. The procedure for entering and working in multi-line mode is described in *User Interfaces* (Section 1.3).

Commas are required between each **for** expression; no comma is required after the last **for** expression.

CODE recode # age with 1 for age < 21, 2 for age >= 21 and age < 30, 3 for age >= 31 and age < 40, 4 for age >= 41 and age < 50, 5 for age >= 50 EXAMPLE (gdt . gssocc) \
1 recode educ with
2 1 for educ <= 8,
3 2 for educ > 8 and educ <= 12,
4 3 for educ > 12
5 /
(gdt . * gssocc) \
1 report freq
2 use educ
3 /
CASES PROCESSED BY THIS PROCEDURE:
337 cases were kept out of 337.
0 deleted because of missing values.

educ		3.00000	****
			1
Valid	337.0000		1
Missing	0.0000		1
Mean	2.4154		****
Std Dev	0.6264		1
Variance	0.3924		
Mode	3.0000		1
Minimum	1.0000		1
Maximum	3.0000	1.00000	***

		Percents	5]	Percents	
Value	Count	Cell	Cum	Value	Count	Cell	Cum
1	25	7.42	7.42	3	165	48.96	100.00
2	147	43.62	51.04				
Total N	337						



SEE ALSO code

remove

recover

PURPOSE	Recovers a data set that has been removed.
FORMAT	recover data_set_name
REMARKS	The file associated with the removed data set is renamed by dropping the .removed extension; the .removed file must still be on the disk.
SEE ALSO	remove

remove

	PURPOSE	Closes and renames the specified data set.
--	---------	--

- FORMAT **remove** handle
- **REMARKS** The data set must be open.

The data set is closed and the associated file is renamed by appending a .removed extension; any previous extension in the filename remains intact.

To delete a data set file from the disk, use the operating system commands for deleting files.

- CODE remove test
- EXAMPLE (gdt test) remove test

/data/test.dat renamed to /data/test.dat.removed
(gdt)

SEE ALSO recover

report

PURPOSE Presents data in various formats such as listings, tables, and plo	PURPOSE	Presents data in	various formats	such as listings,	tables, and	plots
--	---------	------------------	-----------------	-------------------	-------------	-------

- FORMAT **report** *report_name*
- REMARKS The report statement syntax requires multiple line entries. Procedures for entering multiple line entries are described in *User Interfaces* (Section 1.3).

For available reports enter:

help report

For information on a particular report enter:

help report report_name

CODE report freq

- EXAMPLE
- (gdt freqdata) \
 1 report freq
 2 use age,pay,sex
 3 weight wt
 4 /

report

```
CASES PROCESSED BY THIS PROCEDURE:
 398 cases were kept out of 400.
 2 deleted because of missing values.
                     10.00000 |***************
age
                            | ****
Valid
       585.5600
                            | ******
                            *****
Missing
         0.0000
                            | * * * * * * * * * * * * * * * * *
Mean
         5.6530
                            | * * * * * * * * * * * * * * *
Std Dev
         2.9763
                            | * * * * * * * * *
Variance
         8.8584
                            *****
Mode
          10.0000
                            ****
Minimum
         1.0000
                     1.00000 |**************
Maximum
         10.0000
             Percents
                                      Percents
 Value Count Cell Cum Value Count
                                       Cell
                                             Cum
_____
    1 67.94 11.60 11.60
                           6 62.25 10.63 58.04
                            7 49.54 8.46 66.50
    2 44.42 7.59 19.19
    3 67.52 11.53 30.72
                            8 58.63 10.01 76.51
    4 36.66 6.26 36.98
                            9 65.77 11.23 87.75
    5 61.07 10.43 47.41
                         10 71.76
                                      12.25 100.00
 Total N 586
_____
                     3.00000 |**************
pay
Valid
       587.9800
                           Missing
         0.0000
          1.9748
                           *****
Mean
Std Dev
         0.8008
Variance
         0.6413
Mode
          2.0000
Minimum
         1.0000
                    1.00000 |**************
Maximum
         3.0000
```

rollback

		Percents	S			Percents	;
	Count						
	195.8						
	211.2						
Total	N 588						
sex			F	******	*****	***	
			M	' ******	****		
Valid	587	.9800					
Missing	0	.0000					
		F					
Mode							
Mode		Percents	5			Percent	s
Value	Count	Cell	Cum			Cell	Cun
Value F	Count 360.92	Cell 61.38	Cum 61.38	M	227.06	Cell 38.62	Cur 100.00

(gdt freqdata)

rollback

- PURPOSE Discards all changes since the last commit.
 - FORMAT rollback [[handle, handle, ...]]
- **REMARKS** All changes to the data set since the last **commit** are discarded.

If *handle* is not specified, the active data set is rolled back.

sample

	The frename command is not rolled back.
CODE	rollback
	rollback hist, proj
SEE ALSO	commit
sample	
PURPOSE	Creates a random sample of observations in a data set.
FORMAT	<pre>sample num% [[without]]</pre>
	<pre>sample num_obs [[without]]</pre>
REMARKS	This command modifies the data set by deleting observations; consider using frename before executing sample .
	If % is appended to <i>num</i> , the sample will consist of the specified percentage of observations, otherwise, the data set is modified to contain <i>num_obs</i> observations.
	If without is added, sampling is without replacement, otherwise, it is with replacement.
CODE	sample 10%
	sample 1000
EXAMPLE	(gdt freqdata) stats

select

> freqdata 4 vars, 400 obs /data/freqdata.dat Variable Mean Std Dev Variance Minimum Maximum Valid Missing AGE 5.6784 2.9932 8.9593 1.0000 10.0000 398 2 PAY 1.9675 0.8019 0 0.6431 1.0000 3.0000 400 sex ____ ____ ____ ____ ____ _ _ _ _ ___ WΤ 1.4699 0.3007 0.0904 1.0000 1.9900 400 0 (gdt freqdata) sample 10% (gdt * freqdata) stats > * freqdata /data/fregdata.dat 4 vars, 40 obs Variable Mean Std Dev Variance Minimum Maximum Valid Missing _____ * AGE 6.4872 2.8365 8.0459 1.0000 10.0000 39 1 * PAY 0 1.9750 0.8002 0.6404 1.0000 3.0000 40 * sex ____ ____ ____ ____ ____ _ _ _ _ _ 0.0981 * WT 1.4400 0.3133 1.0000 1.9800 40 0 (gdt * freqdata)

SEE ALSO frename

select

PURPOSESelects observations based on an expression.FORMATselect where expressionREMARKSThis command deletes all observations that do not match the
expression.CODEselect where age >= 21 and age <= 45</th>EXAMPLE(gdt . * tobit) select where y <= -3.9</th>

Statement Reference

Selected 6	1 of 61	rows	from	tobit,	0	rows	dropped
(gdt . *	tobit)						

SEE ALSO delete

show		
PURPOSE	Shows the content of the active data set workspace.	
FORMAT	show	
REMARKS	Each open data set has its own workspace.	
	Use cleanup to remove all data in the workspace that are not variables of the data set.	
CODE	show	
EXAMPLE	(gdt . nlls) show 1200 bytes T MATRIX 150,1 1200 bytes Y MATRIX 150,1	
SEE ALSO	cleanup	
sort		

PURPOSE Sorts the active data set.

FORMAT sort [[unique]] on var1, var2, ...

- REMARKS Use *unique* to exclude duplicate observations—where more than one observation contains the same key variable value, only one observation will be included.
 - CODE sort on age, date

sort unique on age, date

split

- PURPOSE Splits a matrix into individual vectors.
 - FORMAT **split** *name_of_matrix*
- REMARKS Splits a matrix in the data set workspace into individual vectors. The matrix must contain as many columns as there are variables in the data set and the columns must be in the same order as the **1v** variable list.

The number of observations in the data set may change but the number of variables will not.

CODE split statdat

EXAMPLE (gdt maxfact) cat max0
 (gdt maxfact) g max0 = (max0 - meanc(max0)') ./ stdc(max0)'
 Using maxfact workspace
 (gdt maxfact) stats
 > maxfact 4 vars, 100 obs /data/maxfact.dat
 Variable Mean Std Dev Variance Minimum Maximum Valid Missing

____ Y1 0.0275 1.0706 1.1461 -3.1796 2.8096 100 0 Y2 0.0041 0.8206 0.6734 -1.4813 2.7042 100 0 0.1155 0.9598 0.9212 -1.9176 3.8984 ¥3 100 0 ¥4 0.1058 0.8382 0.7025 -2.1307 2.1470 100 0 (gdt maxfact) split max0 (gdt * maxfact) stats > * maxfact 4 vars, 100 obs /data/maxfact.dat Variable Mean Std Dev Variance Minimum Maximum Valid Missing * Y1 0.0000 1.0000 1.0000 -2.9958 2.5987 100 0 * Y2 -0.0000 1.0000 1.0000 -1.8101 3.2904 100 0 * Y3 -0.0000 1.0000 1.0000 -2.1182 3.9413 100 * Y4 -0.0000 1.0000 1.0000 -2.6682 2.4353 100 0 0 (gdt * maxfact)

SEE ALSO cat

stack

PURPOSE Appends observations from the specified data set to the active data set.

FORMAT stack handle

REMARKS Only variables in the source data set with the same names as variables in the active data set will be copied.

This command will not work if the active data set contains variables that are not also contained in the source data set.

CODE stack gssocc

EXAMPLE (gdt .) open maxsimeq (gdt . maxsimeq) open maxnleq (gdt . maxnleq) stats maxnleq 4 vars. 100 obs maxnleg.dat > Variable Mean Std Dev Variance Minimum Maximum Valid Missing 1.4516 1.9119 3.6553 -2.4473 Y1 8.3456 100 0 Y2 1.4347 1.9034 3.6227 -1.7680 7.7942 100 0 X1 0.0581 0.9999 0.9997 -2.1374 2.2291 100 0 X2 -0.0789 1.0497 1.1019 -2.3797 2.0961 100 0 (gdt . maxnleq) stack maxsimeq (gdt . * maxnleq) stats > * maxnleq 4 vars, 200 obs maxnleq.dat Variable Mean Std Dev Variance Minimum Maximum Valid Missing _____ * Y1 1.3815 1.5549 2.4177 -2.4473 8.3456 200 0 * Y2 1.4360 1.5223 2.3174 -1.7680 7.7942 200 0 * X1 0.0324 1.0110 1.0222 -2.6835 2.9954 200 0 * X2 -0.0723 1.0445 1.0909 -3.0756 2.5930 200 0 (gdt . * maxnleq)

stats

Statement Reference

- PURPOSE Computes statistics on the active data set.
 - FORMAT stats [[var1, var2, ...]]
- **REMARKS** If no variables are given, all variables are included.

If no data set is active, statistics are generated for all open data sets.

```
CODE stats
```

stats age, pay

EXAMPLE (gdt . maxnleq) stats maxnleq > 4 vars, 100 obs maxnleq.dat Variable Mean Std Dev Variance Minimum Maximum Valid Missing Y1 1.4516 1.9119 3.6553 -2.4473 8.3456 100 0 Y2 1.4347 1.9034 3.6227 -1.7680 7.7942 100 0 X1 0.0581 0.9999 0.9997 -2.1374 2.2291 100 0 X2 -0.0789 1.0497 1.1019 -2.3797 2.0961 100 0 (gdt . maxnleq)

use

- PURPOSE Makes the specified data set the active data set.
 - FORMAT **use** handle
- **REMARKS** To see open data sets, use the open statement with no arguments.
 - CODE use freqdata
- EXAMPLE (gdt) use freqdata (gdt freqdata)
- SEE ALSO nouse, open, close

vrename

PURPOSE	Renames a variable.			
FORMAT	vrename old_name new_name	2		
CODE	vrename hst newhst			
EXAMPLE	<pre>(gdt .) open hensher (gdt . hensher) lv > hensher MODE TTME INVC INVT GC HINC PSIZE AIRHINC (gdt . hensher) vrename ttme</pre>	numeric numeric numeric numeric numeric numeric numeric numeric	840 obs,	hensher.dat
	<pre>(gdt . * hensher) lv > * hensher MODE * traveltime INVC INVT GC HINC PSIZE AIRHINC (gdt . * hensher)</pre>	<pre>8 vars, numeric numeric numeric numeric numeric numeric numeric</pre>	840 obs,	hensher.dat

SEE ALSO open

vtype

vtype	
PURPOSE	Changes the variable type of a variable.
FORMAT	vtype new_type var1[[, var2,]]
	Valid types are:
	# numeric
	\$ character
	% date
CODE	vtype # sex
EXAMPLE	<pre>(gdt . freqdata) sex = sex \$== "F" (gdt . * freqdata) vtype # sex 1 variables set to type numeric (gdt . * freqdata) lv > * freqdata</pre>

SEE ALSO open

Index

Index

C_____

cat, 4-4
cd, 4-5
cleanup, 4-6
close, 4-6
cmdfile, import, 2-4
code, 4-7
commit, 4-10
complex, import, 2-6
copy, 4-10

create, 4-11

D _____

datarange, export, 3-12 datarange, import, 2-28 datasheet, export, 3-12 datasheet, import, 2-28 dateformat, export, 3-3 dateformat, import, 2-6 delete, 4-13 deletefile, export, 3-13 delimit, import, 2-7 delimited, hard, 2-9 delimited, soft, 2-8 dotops, 4-13 drop, 4-14 drop, export, 3-4, 3-13

Е_____

Excel File Conversion, 2-24, 3-9 Export, 3-1 **export**, 4-15

Index

F _____

finaldelim, export, 3-4 frename, 4-16

G_____

g, 4-16 garch simulation, 1-15 **GDT**, 1-1

Η_____

handle, 1-3 hard delimited, 2-9

I _____

Import, 2-1 import, 4-17 impute, 4-18 input, import, 2-8, 2-28 Introduction, 1-1 invar, import, 2-8 invarline, import, 2-14

Κ_____

keep, 4-20 **keep**, **export**, 3-5, 3-13

L _____

1d, 4-20 linear simulation, 1-15 logit simulation, 1-16 **1v**, 4-21

M _____

merge, 4-22 **model**, 4-23 **msym**, **import**, 2-15

N _____

namerange, export, 3-13 namerange, import, 2-29 names, import, 2-29 namesheet, export, 3-14 namesheet, import, 2-30 nocheck, import, 2-15 noquote, export, 3-5 nouse, 4-26

0_____

obsdelim, export, 3-5 open, 4-26 open, import, 2-16, 2-30 ordered logit simulation, 1-16 ordered probit simulation, 1-16 output, export, 3-5, 3-14 output, import, 2-16, 2-30 outtyp, import, 2-17 outvar, import, 2-18 overwrite, export, 3-6 overwrite, import, 2-31

P_____

p, 4-27 packed ASCII, 2-12 probit simulation, 1-17 **pwd**, 4-28

Q_____

q, 4-29 **quit**, 4-29

R _____

recode, 4-29 recover, 4-32 remove, 4-32 report, 4-33 rollback, 4-35

S _____

Т_____

transformations, 1-4 translate, export, 3-15 translate, import, 2-31 typecase, import, 2-19 U ______

update, export, 3-16 **use**, 4-42 User Interfaces, 1-4

V

vardelim, export, 3-6 vartype, import, 2-19 vartypeline, import, 2-20 vrename, 4-43 vtype, 4-44

W_____

workspace, 1-1 writevarnames, export, 3-7 writevartypes, export, 3-7